EB GUIDE tutorial

Modeling button behavior with EB GUIDE Script

Version 6.7.1.149092

Copyright © 2018 Elektrobit Automotive GmbH

Legal notice

Confidential and proprietary information.

ALL RIGHTS RESERVED. No part of this publication may be copied in any form, by photocopy, microfilm, retrieval system, or by any other means now known or hereafter invented without the prior written permission of Elektrobit Automotive GmbH.

ProOSEK®, tresos®, and street director® are registered trademarks of Elektrobit Automotive GmbH.

All brand names, trademarks and registered trademarks are property of their rightful owners and are used only for description.

1. Tutorial: Modeling button behavior with EB GUIDE Script

NOTE



Default window layout

All instructions and screenshots of this user's guide use the default window layout. If you want to follow the instructions, we recommend to set the EB GUIDE Studio window to default layout by selecting Layout > Reset to default layout.

With EB GUIDE Script you can express property values, actions, or conditions and evaluate them during runtime.

The following instructions guide you through the process of using EB GUIDE Script to model the behavior of a button. The button increases in size when it is clicked and shrinks back to its original size when it reaches a defined maximum size. For best results, work through the steps in the order presented.

Approximate duration: 10 minutes.



Adding widgets

Prerequisite:

- The Main state machine contains an initial state and a view state.
- The initial state has a transition to the view state.
- The content area displays the view.

Step 1

Drag a rectangle from the **Toolbox** into the view.

Step 2

In the Navigation component, click the rectangle, press the F2 key, and rename the rectangle to Background.

Step 3

Drag a rectangle from the **Toolbox** into the **Navigation** component. Place it as a child widget to the Background rectangle.

Step 4

In the **Navigation** component, click the new rectangle, press the **F2** key, and rename the rectangle to Button.

Step 5

Drag a label from the **Toolbox** into the **Navigation** component. Place the label as a child widget to the Button rectangle. Step 6

In the Navigation component, click the label, press the F2 key, and rename the label to Button text.

Your widget hierarchy now looks as follows.

8 ୭୦୯ ⊳ □
Window Layout Language Standard (en
NAVIGATION × +
Filter model elements
<i></i>
 State machines + Main Initial state Default transition View state 1 View 1 Background Button Button Button text Dynamic state machines + Templates +
OUTLINE × +
Filter model elements Image: Constraint of the second se

Figure 1. Widget hierarchy



Configuring the background

Prerequisite:

You completed the previous instruction.

Step 1

In the Navigation component, click the Background rectangle, and go to the Properties component.

Step 2

Next to the width property, click the **button**.

A menu expands.

Step 3 In the menu, click Add link to widget property.

A dialog opens.

 $\underline{Step \ 4}$ In the dialog, go to the view, and select its width property.

<u>Step 5</u> Click Accept.

The dialog closes. The <u>button</u> is displayed next to the width property.

Step 6

Link the height property of the Background rectangle to the height property of the view.

Step 7

Link the ${\tt x}$ property of the <code>Background</code> rectangle to the ${\tt x}$ property of the view.

Step 8

Link the ${\tt y}$ property of the <code>Background</code> rectangle to the ${\tt y}$ property of the view.

The Background rectangle covers the exact size and position of the view.



Defining the maximum button width

A datapool item holds the value for the maximum width of the button. It can be changed during run-time.

Prerequisite:

You completed the previous instruction.

Step 1

In the **Datapool** component, click +.

A menu expands.

<u>Step 2</u> In the menu, click **Integer**.

A new datapool item of type Integer is added.

Step 3 Rename the datapool item to Maximum width.

Step 4 In the Value text box, enter 400.



Configuring the button

Prerequisite:

You completed the previous instruction.

Step 1

In the Navigation component, click the Button rectangle, and go to the Properties component.

<u>Step 1.1</u> Enter 50 in the height text box.

 $\frac{\text{Step 1.2}}{\text{Enter 350 in the } \times \text{ text box.}}$

 $\frac{\text{Step 1.3}}{\text{Enter 215 in the } y \text{ text box.}}$

Step 1.4 Select blue for the fillColor property.

The button is now colored blue.

Step 2

In the Widget feature properties category, click Add/Remove.

The Widget features dialog is displayed.

Step 3

Under Available widget features, expand the Input handling category, and select the Touch pressed widget feature.

Step 4 Click Accept.

The related widget feature properties are added to the Button rectangle and displayed in the **Properties** component.

Step 5

Next to the touchPressed property, click Edit.

```
Step 6
Replace the existing EB GUIDE Script with the following code:
function(v:touchId::int, v:x::int, v:y::int, v:fingerId::int)
     {
         if (v:this.width > dp:"Maximum width") // If the button has grown
                                             // beyond its maximum size...
      {
  // \ldots reset its dimensions to the default values.
  v:this.height = 50
  v:this.width = 100
  v:this.x = 350
  v:this.y = 215
      }
      else // Otherwise...
      {
  // ... increase button size...
  v:this.width += 80
  v:this.height += 40
  // ...and move the button to keep it centered.
  v:this.x -= 40
  v:this.y -= 20
     }
         false
     }
Step 7
Click Accept.
```

You configured the Button rectangle and wrote an EB GUIDE Script which changes the size of the Button rectangle in run-time.



Configuring the button text

Prerequisite:

You completed the previous instruction.

Step 1

In the Navigation component, click the Button text label, and go to the Properties component.

Step 2 Enter grow! in the text text box. Step 3

Link the width property of the Button text label to the width property of the Button rectangle.

Step 4

Link the height property of the Button text label to the height property of the Button rectangle.

 $\frac{\text{Step 5}}{\text{Enter 0 in the } \times \text{ text box.}}$

 $\frac{\text{Step 6}}{\text{Enter 0 in the }_{Y} \text{ text box.}}$

<u>Step 7</u> Next to the horizontalAlign property, click =.

Now the Button text label and the Button rectangle are equal in size and position.



Saving and testing the EB GUIDE model

Prerequisite:

- You completed the previous instruction.
- Step 1

To save the project, click \square in the command area.

Step 2

To start the simulation, click \triangleright in the command area.

Result:

The simulation starts the EB GUIDE model you created. It behaves as follows.

1. First, it displays a grey screen with a blue button in its center. The screen looks as follows.



Figure 2. Result

- 2. Whenever you click the button, it increases in size but keeps its position at the center of the screen.
- 3. As soon as the button width reaches the value of the Maximum width datapool item, it shrinks back to its original size and position.